

SonoBat 4.5.0 / OS11 Big Sur

SonoBat users have reported that after upgrading their Apple operating system to the latest OS11 Big Sur, their SonoBat software fails on launch. This document shows the changes needed to enable SonoBat to run successfully.

1. In **'Finder'** go to **'Applications'**, **'Utilities'** then **'Terminal'**
2. Copy and paste the following lines one by one into Terminal and execute each with the return key;

`defaults write com.sonobat.sonobat450 NSGraphicsContextAllowOverRestore -bool YES`

`defaults write com.sonobat.sonobat450 NSViewAllowsRootLayerRestore -bool NO`

`defaults write com.sonobat.SonoBat450DataWizardUK NSGraphicsContextAllowOverRestore -bool YES`

`defaults write com.sonobat.SonoBat450DataWizardUK NSViewAllowsRootLayerRestore -bool NO`
3. Now turn off and restart your MAC. SonoBat will now open as before.